Simple OpenMP




mjb@cs.oregonstate.edu



openmp-simple.pptx

mjb - March 14, 2023



3

Much of your use of OpenMP will be accomplished by issuing C/C++ "pragmas" to tell the compiler how to build the threads into the executable

#pragma omp directive [clause]

That's it! That's where the compiler comes in.

But, as you are about to find out, doing parallel processing *at all* is not difficult.

The trick is doing parallel processing *well*. That's where *you* come in.



mjb - March 14, 2023

Using OpenMP on Linux

g++ -o proj proj.cpp -lm -fopenmp

Using OpenMP in Microsoft Visual Studio

- 1. Go to the Project menu → Project Properties
- 2. Change the setting Configuration Properties \to C/C++ \to Language \to OpenMP Support to "Yes (/openmp)"

If you are using Visual Studio 2019 and get a compile message that looks like this: 1>c1xx: error C2338: two-phase name lookup is not supported for C++/CLI, C++/CX, or OpenMP; use /Zc:twoPhase-then do this:

- 1. Go to "Project Properties" \rightarrow "C/C++" \rightarrow "Command Line"
- 2. Add /Zc:twoPhase- in "Additional Options" in the bottom section
- 3. Press OK



njb – March 14, 2023

larch 14, 2023

Seeing if OpenMP is Supported on Your System

#ifdef _OPENMP
fprintf(stderr, "OpenMP version %d is supported here\n", _OPENMP);
#else
 fprintf(stderr, "OpenMP is not supported here – sorry!\n");
 exit(0);
#endif

This gives you a year and month of the OpenMP you are using

To get an OpenMP version number:

OpenMP 5.0 - November 2018

OpenMP 4.5 - November 2015

OpenMP 4.0 - July 2013

OpenMP 3.1 - July 2011



- By default, flip is using g++ 4.8.5, which uses OpenMP version 3.1
- flip's g++ 9.2.0 uses OpenMP version 4.5
- · Looks like Visual Studio 2019's is even older (?)

mjb - March 14, 2023

5

Threads

6

We will get into more detail pretty soon, but for now, know that a thread is an independent execution path for your code to take.

Threads are at their very best when each one can run on a separate hardware core.



njb – March 14, 2023

```
#ifndef _OPENMP
fprintf( stderr, "OpenMP is not supported – sorry!\n" );
exit( 0 );
#endif

How to find out how many cores your system has:
int numprocs = omp_get_num_procs();

How to specify how many OpenMP threads you want to reserve starting now:
omp_set_num_threads( num );

How to use one thread per core:
omp_set_num_threads( omp_get_num_procs() );
University
Computer Graphics
```

